

Vis_cal

Xie Yu

1 介绍

Vis_cal用于计算润滑油的粘度系数和温度，参考于ISO 6336-22^[1]

2 原理

2.1 运动粘度

The kinematic viscosity at bulk temperature, $\nu_{\theta M}$, can be calculated from the kinematic viscosity at 40 °C, ν_{40} , and the kinematic viscosity at 100 °C, ν_{100} . Extrapolation for temperature higher than 140 °C should be confirmed by measurement.

$$\log[\log(\nu_{\theta M} + 0.7)] = A \cdot \log(\theta_M + 273) + B \quad (1)$$

where

$$A = \frac{\log[\log(\nu_{40} + 0.7)/\log(\nu_{100} + 0.7)]}{\log(313/373)} \quad (2)$$

$$B = \log[\log(\nu_{40} + 0.7)] - A \cdot \log(313) \quad (3)$$

where

θ_M is the bulk temperature.

ν_{40} is the kinematic viscosity of the lubricant at 40 °C

2.2 密度

If the density of the lubricant at bulk temperature, $\rho_{\theta M}$, is not available, it can be approximated based on the density of the lubricant at 15 °C according to

$$\rho_{\theta M} = \rho_{15} \cdot \left[1 - \frac{(\theta_M + 273) - 288}{15\rho_{15}}\right] \quad (4)$$

where


ρ_{15} is the density of the lubricant at 15 °C according to the lubricant data sheet

θ_M is the bulk temperature

If no data for ρ_{15} is available, then below formula can be used for approximation of mineral oils

$$\rho_{15} = 43.37\log\nu_{40} + 805.5 \quad (5)$$

3 类结构



输入 input:

- T : 温度

参数 params:

- Material : 润滑油的材料属性

输出 output :

- Rou : 润滑油在该温度下的密度
- Vis1 : 该温度下运动粘度系数
- Vis2 : 该温度下动力粘度系数
- B : 参数B
- A : 参数A

4 案例



以ISO-VG 100为例，计算70°C时的运动粘度系数。

```
1 %% Caculate the vis
2 S=RMaterial('Lubricant');
3 Mat=GetMat(S,3);
4 inputStruct1.T=70;
5 paramsStruct1.Material=Mat{1,1};
6 Vis=method.Vis_cal(paramsStruct1, inputStruct1);
7 Vis=Vis.solve();
8 %% Plot vis, rou&Tempearture curve
9 x=(30:10:150)';
```

```

10 y1=NaN(numel(x),1);
11 y2=NaN(numel(x),1);
12 for i=1:numel(x)
13     Vis=input.T=x(i);
14     Vis=Vis.solve();
15     y1(i)=Vis.output.Vis1;
16     y2(i)=Vis.output.Rou;
17 end
18 figure
19 plot(x,y1)
20 title('Kinematic Viscosity & Temperature Curve')
21 xlabel('Temperature (°C)')
22 ylabel('Kinematic Viscosity (mm2/s)')
23 figure
24 plot(x,y2)
25 title('Density & Temperature Curve')
26 xlabel('Temperature (°C)')
27 ylabel('Density (g/cm3)')

```



5 参考文献

[1] ISO\TR 6336-22